

KABABALI EA V3.30

COMPLETE USER MANUAL / KUMPLETONG GABAY

Kumpletong Gabay sa Pag-install, Pagbasa ng Signal, Auto Trading,
Website Overwrite, Profit Protection, at CSV Audit



ITEM	DETAIL
Exact source / Eksaktong source	KABABALI_EA_V3_30.mq5
MQL5 version	3.30
Platform	MetaTrader 5 (MT5)
Source status	ACTIVE TEST CANDIDATE
Source SHA-256	c47a36e3caa7fb2c3c593d989d4adcc4cd4382fa00c237b4fd4d3e9b8500926c

CRITICAL RISK NOTICE / MAHALAGANG BABALA

This EA can place, reverse, and close real trades when permissions allow. No indicator, EA, dashboard, or AI can guarantee profit. Spread, slippage, latency, broker rules, market gaps, and sudden reversals can change the final result. Use only risk capital and verify the first sessions at the minimum lot size. / Ang EA na ito ay maaaring magbukas, mag-reverse, at magsara ng totoong trade. Walang garantiya ng kita. Gumamit lamang ng perang kaya mong mawala at bantayan ang unang live sessions sa minimum lot.

CONTENTS / NILALAMAN

1. Purpose, scope, and important behavior
2. Quick start installation and activation
3. Recommended first-use profiles
4. How the bot makes a decision
5. How to read the MT5 panel
6. Local BUY/SELL confirmation logic
7. Website Overwrite Signal Confirmation
8. Order execution, one-position, and reversal rules
9. SL/TP construction
10. Quick Profit Pullback and Sure Profit
11. Account tiers and feature access
12. Complete input reference
13. CSV audit log
14. Troubleshooting and common Gate reasons
15. Daily operating checklist and safe shutdown
16. Glossary and support package

HOW TO USE THIS MANUAL

For daily operation, read Sections 2, 4, 5, 7, 10, and 15 first. For changing settings, use Section 12. When a trade is blocked or behaves unexpectedly, use Sections 13 and 14 together with the daily CSV file.

1. PURPOSE, SCOPE, AND IMPORTANT BEHAVIOR *Layunin, saklaw, at mahahalagang behavior*

KABABALI EA V3.30 is an MT5 Expert Advisor that builds local confirmation-line signals, applies entry filters, sends market orders, manages reversal, places SL/TP, protects floating profit, writes a daily CSV audit, and synchronizes with the Kababali website/mobile bridge when the account tier allows it.

Ang V3.30 ay may dalawang posibleng pinagmumulan ng trade decision: (1) local MT5 confirmation logic, at (2) fresh website OVERWRITE confirmation. Kapag may valid overwrite, iyon ang pumapalit sa local confirmation at SL/TP para sa signal na iyon.

VERY IMPORTANT: TREND IS NOT THE SAME AS SIGNAL

The panel Trend can follow the newest live candle, while Signal uses the confirmed execution state. With CLOSED BAR ONLY enabled, Trend may flip inside the current candle but Signal can remain WAIT. Always use Signal + Gate + Reason to know whether an order is actually ready.

- Fixed lot only: LOTS is not automatically calculated from account balance or percentage risk.
- An arrow or Trend label does not prove an order opened. Spread, tier, permissions, filters, position rules, margin, session, or invalid stops may still block execution.
- There is no built-in news filter, daily-loss limit, equity stop, or maximum-trades-per-day input in this source.
- The EA counts only positions with the exact chart symbol and the effective Magic Number.
- The source header identifies this build as an ACTIVE TEST CANDIDATE; continue validating with CSV evidence.

2. QUICK START: INSTALLATION AND ACTIVATION *Mabilis na pag-install at pag-activate*

2.1 Install and compile

1. In MT5, open File > Open Data Folder.
2. Open MQL5 > Experts and copy KABABALI_EA_V3_30.mq5 into that folder.
3. Open MetaEditor (F4), open the source file, then Compile (F7). Confirm 0 errors.

- Return to MT5. In Navigator > Expert Advisors, right-click Refresh if V3.30 is not visible.
- Open the intended symbol and timeframe. The bot uses the exact chart symbol, including broker suffixes such as GOLD#.
- Attach KABABALI EA V3.30 to the chart and review the Inputs tab before pressing OK.

2.2 Enable WebRequest and API verification

- Go to Tools > Options > Expert Advisors.
- Enable Allow WebRequest for listed URL.
- Add <https://kababali.com> to the allowed URL list.
- Paste the website EA key into KABABALI API KEY in the EA Inputs.
- After loading, confirm the footer shows API:YES and the correct account tier. For Platinum bridge use, confirm SYNC:OK.

API KEY SAFETY

The key is an MT5 input and is not hard-coded in the source. Do not share screenshots that expose the key. A missing or denied key blocks live auto execution outside Strategy Tester.

2.3 Enable trading permissions

- In the EA properties, enable Allow Algo Trading.
- Turn on the main MT5 Algo Trading button.
- Confirm the panel shows AutoTrade: ON and Gate is not blocked by permissions, tier, spread, or session.
- Start with LOTS = 0.01 while validating live execution.

STRATEGY TESTER NOTE

WebRequest and live website synchronization are skipped in Strategy Tester. Tester mode receives full tier access for local feature testing, but it does not validate the real API, bridge, or website overwrite flow.

3. RECOMMENDED FIRST-USE PROFILES *Mga panimulang setup*

3.1 Source default profile

SETTING	DEFAULT	WHAT IT MEANS
LOTS	0.01	Fixed minimum-style test volume; broker minimum may differ.
MAX SPREAD POINTS	35	New entry blocked when current spread is above 35 points.
ONE POSITION ONLY	true	Blocks another same-direction EA position.
REVERSE ON OPPOSITE SIGNAL	true	A confirmed opposite signal may close the old direction and open the new direction.
CLOSE OPPOSITE ONLY IF PROFIT	false	Default can reverse even when the old trade is losing.
SIGNAL CLOSED BAR ONLY	true	Uses completed candles when Silver/Gold/Platinum accuracy access is active.
CONFIRMATION CANDLES	2	Default local confirmation sequence.
QUICK PROFIT / SURE PROFIT	ON	Effective only for Platinum/full access.

3.2 Conservative verification profile

For the first live verification, the following profile reduces moving parts. This is guidance, not a profit guarantee.

SETTING	START VALUE	REASON
LOTS	0.01	Keep the smallest intended live volume.
ONE POSITION ONLY	true	One matching position at a time.
REVERSE ON OPPOSITE SIGNAL	false	Prevents automatic close-and-reverse while you study CSV results.

SETTING	START VALUE	REASON
CSV AUDIT LOG	true	Keep all three logging options enabled.
QUICK PROFIT PULLBACK	true	Keep the +0.50 pullback layer active if Platinum.
USE TRADING SESSION	optional	Use broker/server hours only after checking the server clock.

CHANGE ONE VARIABLE AT A TIME

Do not lower several filters and change profit protection simultaneously. Make one change, collect a complete daily CSV, then compare blocked signals, entries, exits, and close reasons.

4. HOW THE BOT MAKES A DECISION *Paano gumagawa ng decision ang bot*

STEP	STAGE	ACTION
1	Market data	Reads exact chart candles, Bid/Ask, spread, EMA, ATR, RSI, ADX/+DI/-DI, Bollinger, Momentum.
2	Candidate	Detects a new trend break or a fresh EMA reclaim/touch continuation.
3	Confirmation	Checks the required candle sequence and BUY-only stability rules.
4	Filters	Applies RSI, ADX, whipsaw, master trend, BB, Momentum, candle body/color as applicable.
5	Execution Gate	Checks API/tier, Algo Trading, symbol mode, spread, session, position rules, SL/TP, and margin.
6	Market order	Uses live Ask for BUY or live Bid for SELL; broker may fill at a different price.
7	Protection	Manages Quick Profit first, then Sure Profit state, SL/TP, and opposite-signal behavior.
8	Audit	Writes gate changes, candles, orders, deals, exits, and profit-protection events to CSV.

VISUAL SIGNAL VS EXECUTION GATE

A chart arrow is evidence that the signal logic qualified at that candle. The order still needs an ALLOW/OVERRIDE execution path. Read Signal, Gate, and Reason together.

5. HOW TO READ THE MT5 PANEL *Pagbasa sa panel*

PANEL AREA	MEANING
Header	EA version, symbol/timeframe, spread limit, latency, LIVE/OFFLINE.
Signal	Confirmed local or website execution direction. WAIT means no executable direction.
Trend	Latest live directional reading; it can change before the candle closes.
Price / Confirm	Current Bid and the live confirmation-line reference.
RSI	PASS, FAIL, or OVERSOLD according to current direction.
ADX	Trend-strength reading. WEAK means below the minimum threshold.
BB	Band width in ATR and EXPANDING/CONTRACTING/NARROW status.
MOM	BULLISH, BEARISH, NEUTRAL, OFF, or tier lock.
WHIPSAW	Recent flip count versus block threshold, e.g. 2/2 BLOCKED.
Trade Plan	WAIT, confirming, blocked, ready, or active-position details.
SureProfit	WAIT, TOUCHED, ARMED, or CONFIRM; shows target/arm/peak/lock.
AutoTrade / Gate	Whether entry permission is enabled and the current gate state.
Reason	Primary reason for WAIT, BLOCK, OVERWRITE, close, or permission issue.
Footer	API status, account tier, access package, and website sync state.

5.1 Typical Gate values

GATE	INTERPRETATION
WAIT	No confirmed executable signal yet, or confirmation is still forming.
BLOCK	A filter, permission, position, spread, session, margin, or invalid override prevents execution.
OVERRIDE	A fresh, allowed website overwrite has replaced local confirmation.
ALLOW	The broker accepted the market order.
CLOSED	Quick Profit or Sure Profit successfully closed the EA position.

COLOR GUIDE

Green usually means BUY/pass/profit; red means SELL/fail/loss; orange means weak, blocked, or caution; silver means neutral/wait; the panel border/accent follows the verified account tier.

6. LOCAL BUY/SELL CONFIRMATION LOGIC *Local confirmation rules*

6.1 Confirmation line and candidate

The local confirmation line is based on EMA 21 plus or minus ATR x 0.35 by default. A BUY trend can be triggered by a qualified close above the upper line; a SELL trend can be triggered by a qualified close below the lower line. A fresh EMA reclaim/touch in the existing trend can also create a continuation candidate.

```
Upper trigger = EMA(21) + ATR(14) x 0.35
Lower trigger = EMA(21) - ATR(14) x 0.35
BUY candidate: qualified close above upper trigger OR bullish EMA reclaim/touch
SELL candidate: qualified close below lower trigger OR bearish EMA reject/reclaim
```

6.2 General confirmation filters

CHECK	DEFAULT RULE
RSI BUY	RSI must be at least 52.0.
RSI SELL	RSI must be from 35.0 through 48.0; below 35 is blocked as oversold.
Candle color	BUY candle bullish; SELL candle bearish when enabled.
EMA slope	Fast EMA must slope with the direction when accuracy access is active.
Body size	Candle body must be at least 0.15 ATR by default.
ADX	At least 23.5 by default.
Whipsaw	Blocked when recent flips are 2 or more inside the 10-candle lookback.
Master trend	Blocks clear counter-trend entries; BUY has additional strict structure rules.
Bollinger	Width must be at least 2.0 ATR; BUY above middle band, SELL below middle band.
Momentum	BUY strictly above 100; SELL strictly below 100.

6.3 Extra BUY protection in V3.30

- At least two stable closed BUY candles, even if the custom confirmation input is set below 2.
- On the last two BUY confirmation candles: trend remains BUY, fast EMA rises, close stays above fast EMA, and +DI is strictly above -DI.
- When the master trend filter is active: slow EMA must rise, fast EMA must be above slow EMA, and close must be above slow EMA.
- The final BUY close cannot be more than 1.25 ATR above the fast EMA, reducing late chase entries.
- A fresh reversal BUY needs a pullback into the fast-EMA zone followed by a bullish reclaim close.
- Immediately before order submission, the EA rechecks live trend, live price versus fast EMA, +DI/-DI, fast/slow alignment, and extension. A stale BUY is cancelled.

6.4 SELL confirmation

SELL follows the general confirmation sequence and filters. The special two-bar DI/master/retest guard described above is BUY-only in this source. This does not mean every SELL will win; it only means the extra V3.27-V3.30 structure patch was designed specifically for BUY.

WHY SIGNAL CAN STAY WAIT WHILE TREND CHANGES

The live Trend can show BUY or SELL inside the current M1 candle. The default confirmed Signal waits for completed candles and the full 2-candle sequence. This is intentional protection against split-second flips.

7. WEBSITE OVERWRITE SIGNAL CONFIRMATION Manual/admin

confirmation mula sa website

V3.30 can read a fresh admin-published overwrite from the existing Kababali bridge. The overwrite can replace the local confirmation direction and order SL/TP while it is active, allowed, valid, and not expired.




Figure 1. Website decision map and Overwrite Signal Confirmation example. Prices are illustrative and change live.

7.1 Requirements before an overwrite can execute

- API key is verified and the account has Platinum / Full Access.
- Website/mobile bridge is synchronized; default sync interval is 15 seconds.
- `override_active` is true, `override_final_allowed` is true, `direction` is BUY or SELL, and `expiry` is still in the future using GMT.
- SL and TP are present and on the correct side of the live market price.
- Normal execution safety still passes: tier, ENABLE TRADING, Algo Trading permissions, symbol mode, spread, session, position rules, volume, filling mode, and margin.

7.2 What the overwrite replaces and what it does not replace

AREA	BEHAVIOR
Replaced	Local confirmation direction; local RSI/ADX/whipsaw/master/BB/momentum trade-filter recheck; BUY live structure recheck; order SL and TP.
Not replaced	LOTS, account tier, API verification, Algo Trading, spread limit, trading session, one-position/reversal rules, margin, broker permissions, Quick Profit, and Sure Profit.
Entry price behavior	The published website entry is a reference/confirmation line. The actual market order uses the live Ask for BUY or Bid for SELL.
Expiry/clear behavior	Expired, cleared, WAIT, not-allowed, or invalid data cancels the pending overwrite and blocks execution.

HIGH-RISK CONTROL

Because a valid overwrite bypasses the local signal filters, the admin confirmation must already include disciplined direction, entry context, and valid SL/TP. Use a short expiry and clear the overwrite after the intended decision.

7.3 Expected panel messages

```
Gate: OVERRIDE
Reason: OVERWRITE BUY: <website reason>
Reason: OVERWRITE SELL: <website reason>
OVERWRITE WAIT: <reason>
OVERWRITE BLOCK: SL/TP invalid versus live price
OVERWRITE pending signal expired or was cleared
```

8. ORDER EXECUTION, ONE-POSITION, AND REVERSAL RULES

Pag-open, pag-block, at pag-reverse ng position

8.1 Which trades belong to this EA?

The EA manages only positions with the exact chart symbol and the effective Magic Number. Manual trades normally use Magic 0 and are not included. Another chart with the same symbol and Magic Number shares the same position count and protection basket.

DUPLICATE-CHART WARNING

Do not attach multiple copies to the same symbol using the same Magic Number unless you intentionally want them to share positions, Quick Profit, Sure Profit, and reversal decisions.

8.2 Default one-position and reverse behavior

SITUATION	RESULT
Same-direction position exists	Blocked with Same position already open when ONE POSITION ONLY = true.
Opposite position exists; Reverse OFF	Blocked with Opposite position open.
Opposite position exists; Reverse ON	EA closes the old direction, refreshes live price/stops, then attempts the new market order.
Close opposite only if profit = false	The old position may be closed and reversed even while losing.
Close opposite only if profit = true	Gold/Platinum only: opposite basket must be profitable and minimum profit points must reach current spread + reverse buffer.
Quick Profit uses opposite arrow	When the armed Quick Profit closes on a confirmed opposite arrow, that exact arrow is consumed as exit-only; no immediate reverse on the same signal.

8.3 Pending signal expiry

A qualified signal can be queued briefly if execution is not completed immediately, but it remains valid only for the current decision candle. Old pending arrows expire instead of being carried into the next candle. Website overwrite pending signals also expire when the override is cleared, changed, or expires.

8.4 Broker and account checks

- Valid lot after broker volume normalization.
- Supported symbol filling mode and valid Bid/Ask.
- Symbol allows the requested direction and new positions.
- Spread is within MAX SPREAD POINTS.
- Enough free margin is available before the order request.
- Broker must return a successful retcode and a real deal number.

9. SL/TP CONSTRUCTION *Paano ginagawa ang Stop Loss at Take Profit*

9.1 Local ATR mode - default

ITEM	DEFAULT BEHAVIOR
SL	Entry +/- ATR x 2.5; minimum 80 points.

ITEM	DEFAULT BEHAVIOR
TP	Entry +/- ATR x 6.0; minimum 120 points.
Direction	BUY places SL below and TP above; SELL places TP below and SL above.
Broker adjustment	The EA adjusts distances and tick size to satisfy broker stop-level rules.

9.2 Fixed-points mode

When USE ATR SL/TP = false and Gold/Platinum custom stop access is available, the default fixed values are 100 points SL and 150 points TP. Minimum-distance checks still apply.

9.3 Tier behavior

Bronze and Silver use built-in safe ATR defaults: ATR stops ON, SL 2.5 ATR, TP 6.0 ATR, minimum SL 80 points, minimum TP 120 points. Gold and Platinum may customize the visible SL/TP settings.

9.4 Website overwrite stops

For an overwrite, the website SL and TP replace local ATR/fixed construction. They must be valid versus the live market price. The actual entry remains a live market fill, so an overwrite can be blocked if price movement makes the published stops invalid before execution.

10. QUICK PROFIT PULLBACK AND SURE PROFIT *Dalawang hiwalay na profit-protection layer*

10.1 Quick Profit Pullback - default +0.50 arm

PHASE	DEFAULT RULE
Arm	When matching EA floating P/L reaches +0.50 account currency, protection becomes ARMED. It does not close on the first touch.
Peak	Tracks the best floating profit after arming.
Normal pullback close	While still positive: profit gives back at least 0.15 from peak AND at least 2 of 3 adverse checks agree: opposite live trend, adverse fast-EMA cross, opposite DI dominance.
Confirmed opposite	While positive, a fully confirmed opposite signal can close immediately after arming and is consumed as exit-only.
Emergency floor	After arming, a request to close occurs when floating profit falls to +0.05 or lower.
Priority	If Sure Profit has already reached its target-touch state, Quick Profit stands down and Sure Profit takes control.

NOT A GUARANTEED +0.50 EXIT

The +0.50 value is the arming threshold, not a guaranteed final fill. Tick speed, spread, slippage, commission, and broker execution can produce a lower or higher realized result.

10.2 Sure Profit - default target 4.00

STATE / RULE	DEFAULT BEHAVIOR
WAIT	Floating profit has not reached 4.00.
TOUCHED	Profit reaches 4.00. No immediate close. The bot waits for headroom.
ARMED	Peak reaches 4.60 = target 4.00 + arm buffer 0.60.
Fixed lock	Default mode keeps the protection lock at 4.00.
Retrace confirmation	When profit retraces to 4.00 or below after arming, it must remain there for 3.0 seconds before close.
Recovery cancel	If profit recovers to 4.05 before confirmation, the pending close is cancelled.
Emergency giveback	Immediate close request at lock - 0.50, which is 3.50 under default fixed mode.
Trail mode	Optional: lock becomes max(target, peak - 0.50).

BASKET SCOPE

Profit protection uses the combined floating profit + swap of positions matching the exact symbol and effective Magic Number. Default ONE POSITION ONLY keeps this simple. With multiple matching positions, the protection acts on the matching basket.

11. ACCOUNT TIERS AND FEATURE ACCESS *Package access ayon sa verified website tier*

TIER	PANEL ACCESS	EFFECTIVE FEATURES
Basic / Tier 1	WATCH MODE	Visual signals and popup alerts; no auto orders.
Bronze / Tier 2	CORE AUTO	Auto trading. Accuracy filters are locked. Uses built-in Magic 777711, slippage 30, and safe ATR stops.
Silver / Tier 3	ACCURACY	Adds closed-bar/candle confirmation, EMA slope/body, ADX, whipsaw, master EMA, Bollinger, and Momentum.
Gold / Tier 4	TRADE CONTROL	Adds custom Magic Number, slippage, SL/TP controls, and profit-only reverse option.
Platinum / Tier 5	FULL ACCESS	Adds Sure Profit, Quick Profit, trading session, website/mobile bridge, and overwrite confirmation.

INPUTS CAN BE VISIBLE BUT LOCKED

The Inputs tab can show settings that the current account tier does not activate. The panel footer and startup logs show the effective tier and access. Strategy Tester behaves as full access but skips real API/bridge communication.

12. COMPLETE INPUT REFERENCE *Lahat ng visible Inputs at default values*

Defaults below are taken from the exact uploaded V3.30 source. "Tier" identifies the minimum practical access level for the feature to take effect.

DISPLAY

INPUT	DEFAULT	TIER	GUIDE
SHOW PANEL	true	All	Show/hide the compact MT5 information panel.
DRAW CONFIRM LINE	true	All	Draw the historical/local confirmation line.
DRAW SIGNAL ARROWS	true	All	Draw qualified historical BUY/SELL arrows.
POPUP ALERTS	true	All	Popup once for a new qualified arrow; alert does not prove an order opened.

KABABALI API

INPUT	DEFAULT	TIER	GUIDE
KABABALI API KEY	blank	All live	Website license key. Required for live tier verification; keep private.

CSV AUDIT LOG

INPUT	DEFAULT	TIER	GUIDE
ENABLE CSV AUDIT LOG	true	All	Create daily CSV files in MQL5/Files.
LOG CLOSED CANDLE CHECKS	true	All	Record each completed-candle evaluation.
LOG BLOCKED / WAIT CHANGES	true	All	Record Gate/Reason changes instead of relying only on Experts.
LOG TRADE OPEN / CLOSE EVENTS	true	All	Record requests, broker deals, and close classifications.

MAIN

INPUT	DEFAULT	TIER	GUIDE
ENABLE TRADING	true	Bronze+	Allows new orders. Profit-protection management remains separate.
LOTS	0.01	Bronze+	Fixed requested volume; normalized to broker min/step/max.
MAX SPREAD POINTS	35	Bronze+	0 disables the spread limit; otherwise blocks above the point threshold.
ONE POSITION ONLY	true	Bronze+	Blocks another same-direction matching position.
REVERSE ON OPPOSITE SIGNAL	true	Bronze+	Close opposite matching position and attempt the new direction.

SIGNAL

INPUT	DEFAULT	TIER	GUIDE
EMA PERIOD	21	All	Fast EMA used by the confirmation line and reclaim logic.
ATR MULTIPLIER	0.35	All	Distance of upper/lower trigger line from EMA.
USE RSI FILTER	true	All	Enable RSI direction thresholds.
BUY RSI LEVEL	52.0	All	BUY requires RSI >= this level.
SELL RSI LEVEL	48.0	All	SELL requires RSI <= this level unless oversold block applies.
SELL RSI OVERSOLD BLOCK BELOW	35.0	All	SELL is blocked when RSI is below this value.
USE CANDLE COLOR	true	All	BUY needs bullish candle; SELL needs bearish candle.

ACCURACY FILTERS

INPUT	DEFAULT	TIER	GUIDE
SIGNAL CLOSED BAR ONLY	true	Silver+	Use the last completed candle rather than the live candle.
USE CANDLE CONFIRMATION	true	Silver+	Require the confirmation sequence when closed-bar mode is active.
CONFIRMATION CANDLES (CUSTOM)	2	Silver+	General confirmation-bar count. BUY still enforces at least 2.
USE EMA SLOPE FILTER	true	Silver+	Fast EMA must slope in the signal direction.
MIN CANDLE BODY ATR	0.15	Silver+	Minimum candle body as a fraction of ATR; 0 disables.
USE ADX FILTER	true	Silver+	Require trend strength.
ADX PERIOD	14	Silver+	ADX/+DI/-DI Wilder period.
MINIMUM ADX	23.5	Silver+	Entry/confirmation blocked below this ADX.
USE WHIPSAW FILTER	true	Silver+	Block rapidly alternating trend changes.
WHIPSAW FILTER CANDLES (CUSTOM)	10	Silver+	Lookback window for trend flips.
WHIPSAW BLOCK AT FLIP COUNT	2	Silver+	Blocked when flips are greater than or equal to this threshold.

MASTER TREND FILTER

INPUT	DEFAULT	TIER	GUIDE
USE MASTER TREND FILTER	true	Silver+	Use slow EMA context; BUY also uses strict slow/fast alignment.
MASTER EMA PERIOD	100	Silver+	Slow/master EMA period.
MASTER SLOPE LOOKBACK CANDLES	3	Silver+	Compare the master EMA with this many candles earlier.

BB / MOMENTUM

INPUT	DEFAULT	TIER	GUIDE
USE BOLLINGER FILTER	true	Silver+	Require adequate band width and correct side of the middle band.
BOLLINGER PERIOD	20	Silver+	Bollinger calculation period.
BOLLINGER DEVIATION	2.0	Silver+	Band standard-deviation multiplier.
MINIMUM BB WIDTH ATR	2.0	Silver+	Block when band width is below this ATR multiple.
USE MOMENTUM FILTER	true	Silver+	Use Momentum direction check.
MOMENTUM PERIOD	14	Silver+	Momentum calculation period.
BUY MOMENTUM LEVEL	100.0	Silver+	BUY requires Momentum strictly above this level.
SELL MOMENTUM LEVEL	100.0	Silver+	SELL requires Momentum strictly below this level.

SL / TP ON ENTRY

INPUT	DEFAULT	TIER	GUIDE
USE ATR SL / TP	true	Gold+ custom	Use ATR distances; Bronze/Silver always use safe ATR defaults.
SL ATR MULTIPLIER	2.5	Gold+ custom	ATR multiplier for SL.
TP ATR MULTIPLIER	6.0	Gold+ custom	ATR multiplier for TP.
MINIMUM SL POINTS	80	Gold+ custom	Minimum SL distance.
MINIMUM TP POINTS	120	Gold+ custom	Minimum TP distance.
FIXED SL POINTS	100	Gold+ custom	Used when ATR stops are off.
FIXED TP POINTS	150	Gold+ custom	Used when ATR stops are off.
USE SURE PROFIT	true	Platinum	Enable the larger money-based retrace protection.
SURE PROFIT TARGET	4.00	Platinum	Target in account currency; first touch does not close.
SURE PROFIT MODE	FIXED_AT_TARGET	Platinum	Fixed target lock or optional trail-from-peak mode.
SURE PROFIT ARM BUFFER	0.60	Platinum	Headroom above target required before protection arms.
SURE PROFIT RETRACE CONFIRM SECONDS	3.0	Platinum	Time at/below lock before normal close.
SURE PROFIT RECOVERY RESET BUFFER	0.05	Platinum	Recovery above lock that cancels pending retrace close.
SURE PROFIT EMERGENCY GIVEBACK	0.50	Platinum	Immediate floor below the lock during retrace.
TRAIL PULLBACK	0.50	Platinum	Peak-to-lock pullback only in trail mode.
SURE PROFIT EXPERT LOGS	true	Platinum	Write state diagnostics to Experts.
SURE PROFIT LOG INTERVAL SECONDS	10	Platinum	Periodic status interval; state changes log immediately.

QUICK PROFIT PULLBACK

INPUT	DEFAULT	TIER	GUIDE
USE QUICK PROFIT PULLBACK	true	Platinum	Enable the small-profit adverse-pullback layer.
QUICK PROFIT ARM	0.50	Platinum	Arm threshold in account currency; no immediate close.
QUICK PROFIT PEAK GIVEBACK	0.15	Platinum	Required peak giveback before 2-of-3 adverse-pressure close.
QUICK PROFIT EMERGENCY FLOOR	0.05	Platinum	Close request when armed gain nearly disappears.

TRADE MANAGEMENT

INPUT	DEFAULT	TIER	GUIDE
MAGIC NUMBER	777711	Gold+ custom	Unique identifier. Bronze/Silver use built-in 777711.

INPUT	DEFAULT	TIER	GUIDE
SLIPPAGE POINTS	30	Gold+ custom	Maximum requested deviation. Bronze/Silver use built-in 30.
CLOSE OPPOSITE ONLY IF PROFIT	false	Gold+	When true, reverse only if old basket is profitable and has enough profit points.
REVERSE PROFIT BUFFER POINTS	50	Gold+	Required profit points are current spread + this buffer.

TRADING SESSION

INPUT	DEFAULT	TIER	GUIDE
USE TRADING SESSION	false	Platinum	Restrict new entries by broker/server hour.
SESSION START HOUR	4	Platinum	Inclusive start hour, clamped to 0-23.
SESSION END HOUR	23	Platinum	Exclusive end hour. Same start/end means all day; overnight supported.

12.1 Hidden internal defaults

INTERNAL ITEM	VALUE	MEANING
API profile endpoint	https://kababali.com/api/ea/profile	License and tier check.
Bridge sync endpoint	https://kababali.com/api/trading/bridge-sync	Website/mobile synchronization.
Bridge interval	15 seconds	Fresh overwrite can take up to a sync cycle plus latency.
Bridge bars / history	120 bars / 50 deals	Data sent to the website bridge.
ATR / RSI period	14 / 14	Hidden Wilder periods.
BUY minimum stable bars	2	Cannot be lowered by the custom confirmation input.
BUY maximum extension	1.25 ATR	Anti-chase rule above fast EMA.
Lookback / visual bars	5000 / 350	Calculation history and chart drawing range.
Panel	X 12, Y 24, width 375, font 10	Fixed compact panel with auto height.

13. CSV AUDIT LOG *Daily record ng ginagawa ng bot*

13.1 File location and name

Open MT5 > File > Open Data Folder > MQL5 > Files. The bot creates one file per broker/server date, symbol, timeframe, and effective Magic Number.

```
KABABALI_AUDIT_YYYY-MM-DD_SYMBOL_PERIOD_M1_M777711.csv
```

The filename uses the broker/server date. Each row also contains both ServerDateTime and LocalDateTime.

13.2 Main events to review

EVENT	USE
EA_INIT / EA_DEINIT	EA load/remove and initialization state.
BAR_CHECK	Closed-candle signal/indicator snapshot.
GATE_CHANGE	New WAIT/BLOCK/ALLOW/OVERRIDE reason.
SIGNAL_PENDING	Qualified arrow queued for possible execution.
DIAGNOSTIC	Detailed decision or order failure/success.
ORDER / DEAL events	Broker request, entry, close, SL, TP, manual, expert, or reversal classification.
QUICK_PROFIT	New position, armed, new peak, trigger, close success/failure.

EVENT	USE
SURE_PROFIT	WAIT, TOUCHED, ARMED, lock/retrace, recovery, close.

13.3 Important columns

- Signal, Trend, ConfirmDirection, ConfirmCount, ConfirmRequired.
- OHLC, Bid, Ask, SpreadPoints, FastEMA, SlowEMA, ATR, RSI, ADX, PlusDI, MinusDI.
- BBMiddle, BBWidthATR, Momentum, WhipsawFlips.
- Gate, Decision, Reason, LastAction.
- Ticket, Deal, Position, Volume, Entry, SL, TP, Profit, Balance, Equity, FreeMargin.

BEST DEBUGGING PRACTICE

Send the complete CSV file, not only a screenshot. Include the exact trade time, symbol/timeframe, MT5 panel screenshot, and History/Journal screenshot. The CSV shows why the bot decided, while History confirms the actual broker deal.

14. TROUBLESHOOTING AND COMMON GATE REASONS *Mga*

karaniwang dahilan ng WAIT/BLOCK

MESSAGE / REASON	WHAT TO DO
API license not verified / KEY NOT SET	Paste the correct API key; allow https://kababali.com in WebRequest; reload EA.
BASIC WATCH MODE ONLY	Basic tier displays signals but cannot send auto orders; Bronze or higher is required.
Terminal/account algo trading disabled	Enable Allow Algo Trading in EA properties and the MT5 Algo Trading button.
SPREAD DETECT x>35 BLOCK	Wait for lower spread or deliberately change the point limit after checking symbol point size.
WHIPSAW 2/2 BLOCKED	Recent trend flips reached the configured threshold; wait for a cleaner structure.
ADX WEAK / CNDL-EMA-ADX wait	Confirmation sequence or trend strength is incomplete.
RSI BUY FAIL / RSI SELL FAIL	RSI is outside the allowed direction threshold.
RSI OVERSOLD	SELL blocked because RSI is below 35 by default.
MASTER BUY/SELL BLOCK	Price and master EMA slope show clear counter-trend risk.
BB NARROW / BB BUY / BB SELL	Band width or price position versus BB middle failed.
MOMENTUM BUY/SELL	Momentum is not strictly above/below 100 as required.
BUY WAIT: EMA RETEST	Fresh reversal BUY has not completed the required pullback and bullish reclaim.
BUY WAIT: SLOW EMA DOWN / FAST <= SLOW	BUY structure is not yet aligned with the master trend.
BUY BLOCK: LIVE TREND SELL / BELOW FAST EMA	Closed-bar BUY became stale before the order was sent.
Same position already open	A matching same-direction position exists and ONE POSITION ONLY is true.
Opposite position open	Reverse is off, so the EA will not close the old direction.
profit points < required	Profit-only reverse is on, but old trade has not covered spread + reverse buffer.
Session 04:00-23:00	Current broker/server hour is outside the enabled entry session.
OVERWRITE WAIT / NOT ALLOWED	Website override is WAIT, not final allowed, cleared, or expired.
OVERWRITE BLOCK: SL/TP invalid	Website SL/TP is on the wrong side of the current live Bid/Ask.
No money / margin block	Reduce lot or free margin; the EA blocks before sending repeated no-money requests.
SYNC:TESTER SKIP	Normal in Strategy Tester; real website override is not being tested.

14.1 Deal side in MT5 History

OPENING AND CLOSING DEALS USE OPPOSITE SIDES

Opening a BUY appears as a BUY deal; closing that BUY appears as a SELL deal. Opening a SELL appears as a SELL deal; closing that SELL appears as a BUY deal. A later opposite-side row may simply be SL/TP/manual/expert closure, not a new reverse entry.

14.2 Panel text overlap on another laptop

V3.30 wraps the Reason text and auto-sizes panel height. If text still overlaps because of Windows DPI scaling, set Windows Display Scale to 100%, restart MT5, and use a normal chart window size. The panel width and font remain fixed internal defaults.

15. DAILY OPERATING CHECKLIST AND SAFE SHUTDOWN

Checklist bago, habang, at pagkatapos mag-trade

15.1 Before the session

- Correct source/version: panel shows KABABALI AUTO EA V3.30.
- Correct chart symbol and timeframe, including broker suffix.
- API:YES, correct tier, and SYNC:OK when website overwrite is needed.
- AutoTrade ON, MT5 Algo Trading ON, and no permission block.
- LOTS, spread limit, One Position, Reverse, SL/TP, Quick Profit, and Sure Profit reviewed.
- No duplicate chart with the same symbol and Magic Number unless intentional.
- CSV audit options ON and MQL5/Files writable.

15.2 While trading

- Do not trade from Trend alone; use Signal + Gate + Reason.
- Treat OVERWRITE as active only when MT5 panel confirms it; website marking alone is not execution proof.
- Watch spread, latency, and abnormal broker gaps.
- Quick Profit ARMED at +0.50 does not mean the trade has closed.
- Sure Profit TOUCHED at 4.00 does not mean the trade has closed; default arm is 4.60.
- After a manual intervention, record the time and reason so the CSV/History review remains understandable.

15.3 Stop new entries safely

To stop new entries while leaving the EA attached, set ENABLE TRADING = false. This is preferable to turning off MT5 Algo Trading when an existing position still relies on EA-managed protective closes. Turning off Algo Trading can also prevent the EA from closing positions.

15.4 Full shutdown

1. Close or take control of all open positions as intended.
2. Save the daily CSV and take a final panel/History screenshot.
3. Disable Algo Trading or remove the EA from the chart.
4. Confirm no matching pending/open positions remain.

LIVE-TRADING DISCIPLINE

A strong demo result does not guarantee the same live result. Live spread, slippage, latency, liquidity, broker execution, and market regime can be materially different. Use a defined daily loss limit outside the EA because this source does not provide one.

16. GLOSSARY AND SUPPORT PACKAGE *Mabilis na kahulugan at kailangang ipadala sa support*

TERM	MEANING
ATR	Average True Range; volatility measurement used for trigger distance and SL/TP.
EMA	Exponential Moving Average; fast EMA 21 and master EMA 100 by default.
ADX	Trend-strength measure; direction comes from +DI/-DI and price structure, not ADX alone.
+DI / -DI	Directional movement components. V3.30 BUY requires +DI > -DI in strict checks.
Whipsaw	Rapid alternating BUY/SELL trend flips in a short lookback.
Gate	Final execution state: WAIT, BLOCK, OVERRIDE, ALLOW, or CLOSED.
Magic Number	Identifier separating this EA positions from manual/other EA positions.
Point	The broker symbol minimum quoted price unit; not automatically the same as a pip.
Floating P/L	Unrealized position profit/loss, plus swap in the EA basket calculations.

TERM	MEANING
Market order	Order filled at the current broker price, not guaranteed at a displayed reference price.

16.1 When reporting a problem, send all of these

- Exact MQ5 filename and panel version.
- Complete daily KABABALI_AUDIT CSV.
- MT5 panel screenshot showing Signal, Trend, Gate, Reason, tier, and sync.
- MT5 History and Journal/Experts around the exact time.
- Symbol, timeframe, broker/server, lot, and spread at the event.
- For website overwrite: website screenshot, direction, SL, TP, reason, expiry, and whether final allowed was enabled.

FINAL REMINDER

The goal of confirmation and protection is to reduce avoidable low-quality entries and profit giveback, not to eliminate all losses. Review the CSV over multiple complete sessions before judging a setting or changing the strategy.

END OF MANUAL | KABABALI EA V3.30 | Based on exact uploaded source